


Creating and Searching for Dilutions

Creating Dilutions

A new functionality has been added to the application in version 45940 you can create and search Raw Material Dilutions.


Add Raw Material attributes for Dilutions

Specify if the Raw Material is a Solvent. Complete this for each Raw Material that is a Solvent Navigate to Modify a Raw Material on the Key Details Tab select Yes Is Solvent Save.




Formulation CDT - Add Dilution

Navigate to Add a New Formulation Input the Raw Material and concentration Input the Solvent and concentration Save & Check In




Add Formulation attributes for Dilutions

Modify the Formulation on the Key Details Tab select Yes Is Dilution
The Concentration amount, the Dilution Item and Solvent Item will the Populate the below fields.
Save




In View/Modify the Formulations Composition

The Raw Material displays a droplet icon to indicate the Raw Material is contained in a Dilution.




Click on the droplet Icon and a search box will appear select Any and all the existing dilutions available for the Raw Material will be displayed. To narrow the search, enter a concentration range in the Concentration field.



Instant Search in the CDT (Composition Design Tool)

Additionally, in Modify a Formulations Composition the Smart Search now includes the option to filter the CDT Search results for Dilutions. These can now be included or excluded from the results.



Mini Tip

Search for Dilutions in Find Matching Items

Find Matching Items - Dilutions

In Find Matching Items there is a new area 'Dilutions' which enables you to Search for Solvents, Dilutions, Dilution Items, Concentration range, and Solvent Item.

Input the relevant Search Criteria and select Search

A list of the relevant Items will be generated.

